

The Zeevo logo is displayed in a white, lowercase, sans-serif font. It is centered within a horizontal purple banner that features a subtle, repeating pattern of stylized, swirling floral or leaf-like motifs.

MailStar

Palm Pre Setup Guide

Document Version: 1 (10 January 2011)

Please Note: This document is prepared on the basis it is commercial in confidence and is not be disclosed to any third parties without the express written permission of Zeevo Ltd.

Set Up POP – Palm® Pre™

For increased security, we recommend that you use our secure (SSL) servers, as detailed below.

To set up the Palm Pre for POP, perform the following steps:

1. Tap the **Email** icon.




2. If there are no email accounts, tap the **Email** tab and select **Manual Setup**. Proceed to step 3.

If there are already email accounts on the Palm Pre, perform the following steps:

1. Tap the **Email** tab and select **Preferences & Accounts**.
2. Tap the **Add An Account** button.
3. Tap the **Email** tab and select **Manual Setup**.
3. Under **MAIL TYPE**, ensure that **POP** is selected.
4. Under **EMAIL ADDRESS**, enter your entire email address (e.g., myname@mydomain.com).
5. Under **INCOMING MAIL SERVER**, enter the following information in the spaces provided:

- Enter server name—Enter the secure server name:
secure.emailsrvr.com
- USERNAME—Enter your entire email address (e.g., myname@mydomain.com).
- PASSWORD—Enter the password for your email account.
- PORT #—Enter the secure incoming port: **995**
- ENCRYPTION—Tap and select **SSL**.



The screenshot shows a mobile application interface for configuring an email account. It features several input fields and labels:

- MAIL TYPE:** A dropdown menu with "POP" selected.
- EMAIL ADDRESS:** A text field containing "myname@mydomain.com".
- INCOMING MAIL SERVER:** A text field containing "secure.emailsrvr.com".
- USERNAME:** A text field containing "myname@mydomain..." with a blue label "USERNAME" to its right.
- PASSWORD:** A text field with masked characters (dots) and a blue label "PASSWORD" to its right.
- PORT #:** A text field containing "995" with a blue label "PORT #" to its right.
- ENCRYPTION:** A dropdown menu with "SSL" selected and a blue label "ENCRYPTION" to its right.

Under **OUTGOING MAIL SERVER**, enter the following information in the spaces provided:

- Enter server name—Enter the secure server name:
secure.emailsrvr.com
- Use Authentication—Select **ON**.
- USERNAME—(This may auto-populate with the information that you have already entered.)
Enter your entire email address (e.g., myname@mydomain.com).

- **PASSWORD**—(This may auto-populate with the information that you have already entered.)
Enter the password for your email account.
- **PORT #**—Enter the secure incoming port: **465**
- **ENCRYPTION**—Tap and select **SSL**.

SSL ENCRYPTION

OUTGOING MAIL SERVER

secure.emailsrvr.com

Use Authentication ON

myname@mydomain... USERNAME

..... PASSWORD

465 PORT #

SSL ENCRYPTION

Sign In

Tap the **Sign In** button.